

Subject: IRIS DVS and IRIS Inquiry Serial Numbers

Hardware: All

Software: IRIS DVS and Inquiry – All Versions

Release Date: 04/04/06

SUMMARY

During installation of the IRIS DVS and IRIS Inquiry software the user is prompted to enter the serial number of the software. This serial number is then stored in the system Registry and is referenced later for authentication functions.

PROCEDURE TO CHANGE SERIAL NUMBER

This step-by-step procedure describes how to change the serial number stored in the Registry for both IRIS DVS and IRIS Inquiry.

WARNING: Using Registry Editor incorrectly can cause serious problems that may require you to reinstall Windows. IRIS Digital Video Systems cannot guarantee that problems resulting from the incorrect use of Registry Editor can be solved. Use Registry Editor at your own risk.

NOTE: For information about how to edit the registry, view the Changing Keys And Values online Help topic in Registry Editor (Regedit.exe). Note that you should make a back-up copy of the registry files (System.dat and User.dat) before you edit the registry.

1. Open the Windows Registry editor by selecting Start->Run and then enter "REGEDIT" and press "OK"
2. Using the Registry Editor expand the "HKEY_LOCAL_MACHINE" folder.
3. Next expand the "SOFTWARE" folder.
4. Expand the "SECURITY CENTER" folder.
5. If you wish to modify the IRIS DVS serial number expand the "BANKIRIS_NT" folder. If you wish to

modify the IRIS Inquiry serial number expand the "INQUIRY IRIS" folder.

6. Expand the "1.0" folder.
7. To change the entry for the serial number, right click on the "Serial" key and select "Modify" from the drop down list.
8. Type in the new serial number and select "OK".
9. Close the Windows Registry Editor. The new serial number will be automatically read the next time the IRIS software is started.

This completes the upgrade process.